

Package ‘ronfig’

January 12, 2026

Type Package

Title Load Configuration Values

Version 0.0.8

Description A simple approach to configuring R projects with different parameter values. Configurations are specified using a reduced subset of base R and parsed accordingly.

URL <https://timtaylor.codeberg.page/ronfig/>

BugReports <https://codeberg.org/TimTaylor/ronfig/issues>

License GPL-2 | GPL-3

Encoding UTF-8

RoxygenNote 7.3.3

Imports carrier, cli, utils

Suggests knitr, quarto, stats, testthat (>= 3.0.0)

Config/testthat/edition 3

VignetteBuilder quarto

NeedsCompilation no

Author Tim Taylor [aut, cre, cph] (ORCID:
<<https://orcid.org/0000-0002-8587-7113>>)

Maintainer Tim Taylor <tim.taylor@hiddenelephants.co.uk>

Repository CRAN

Date/Publication 2026-01-12 14:30:02 UTC

Contents

load_config	2
Index	5

load_config

*Load configuration***Description**

Load a user defined configuration from file. By default (i.e. when `as_is = FALSE`), `load_config()` requires inputs to be given as uniquely-named lists. It first parses the configuration file looking for a 'default' entry. With no additional arguments this will be returned as a list to the user. If the user specifies an additional list to consider (via the `config` argument) then this list is layered on top (using `utils::modifyList()`).

`list_config()` returns the names of (possible) configurations within the given file. It corresponds to `names(load_config(filename, as_is = TRUE))`.

Usage

```
load_config(
  filename,
  config,
  crates,
  ...,
  as_is = FALSE,
  default = "default",
  strict = TRUE
)

list_config(filename, strict = TRUE)
```

Arguments

<code>filename</code>	Configuration file to read from.
<code>config</code>	If <code>as_is = FALSE</code> , name of entry in configuration file to layer on top of 'default'. If <code>as_is = TRUE</code> then, if specified, this entry will be selected from the configuration and returned.
<code>crates</code>	A list of <code>carrier::crate</code> objects which are used to inject functions in to the environment where the configuration file will be evaluated.
<code>...</code>	Not currently used.
<code>as_is</code>	Should the configuration file be read in as is, without layering on top of the default config? Defaults to <code>FALSE</code> .
<code>default</code>	The default configuration to use. Not used if <code>as_is = FALSE</code> .
<code>strict</code>	If <code>TRUE</code> then configuration files can be specified using only a reduced subset of base R as well as a handful of other functions. See details for more information.

Details

If `strict` is `TRUE` (default), then configuration files can be specified using a reduced subset of base R. By default this is restricted to the following operators and functions:

- `<-`, `=`, `+`, `-`, `*`, `:`
- `$`, `[`, `[[`
- `$<-`, `[<-`, `[[<-`
- `c()`
- `as.Date()`
- `array()`, `matrix()`
- `list()`, `data.frame()`
- `Sys.Date()`, `Sys.time()`
- `seq()`, `sequence()`, and `seq_len()`
- `file.path()`
- `modifyList()`

We also enable a convenience function, `cc`, which automatically quotes input to save typing.

If `strict` is `FALSE` then the entire base namespace, as well as `cc` and `modifyList` are made available.

Users can also inject their own functions in to the evaluation environment by supplying a list of [crates](#) as an additional argument.

Value

If `as_is` = `FALSE` (default), `load_config()` returns a list contain entries corresponding to the chosen config.

If `as_is` = `TRUE` and no config value specified, a list of all entries in the evaluated configuration file. If a config value is specified, this entry is pulled from the list and returned.

`list_config()` returns a character vector of (possible) configurations within the given file. It corresponds to `names(load_config(filename, as_is = TRUE))`.

Examples

```
# load the example configuration
file <- system.file("config.R", package = "ronfig")
cat(readChar(file, file.info(file)$size))

# default configuration
str(load_config(file))

# debug configuration
str(load_config(file, "debug"))

# forecast configuration
str(load_config(file, "forecast"))
```

```
# Injecting crated function
f <- tempfile()
cat("default <- list(a=mean(1:10))", file = f)

# will fail as mean() not available
tryCatch(with(load_config(f), a), error = conditionMessage)

# will work if we inject crated mean
crate <- carrier::crate(function(x) mean(x))
with(load_config(f, crates = list(mean = crate)), a)

unlink(f)
```

Index

`carrier::crate`, [2](#)
`crates`, [3](#)

`list_config (load_config)`, [2](#)
`load_config`, [2](#)